


# App Inventor + IoT: Temperature Sensor

This tutorial will help you connect App Inventor + IoT with a temperature sensor on an [Arduino 101](#) controller. We are also using a [Seeed Grove](#) shield for this tutorial. You do not need to use this board, but it does make things easier. The temperature sensor we recommend is the [Grove temperature & humidity sensor](#).

Before you start you should first complete the [App Inventor + IoT Setup tutorial](#) to set up your Arduino device.

- Connect the temperature sensor to the Grove board in the D4 pin connector. →
- For this tutorial make sure **TEMPERATURE** is set to **ENABLED** and all others are set to **DISABLED**.
- You should also click the → arrow button in the top left to upload the code




```
AIM-for-Things-Arduino101 | Arduino 1.8.1
AIM-for-Things-Arduino101 § Accelerometer.hh Button.hh Camera.hh Console.hh Fingerprint.hh yros
1 #define NAME "App Inventor" // no more than 11 characters
2 #define DEBUGGING ENABLED
3
4 #define ACCELEROMETER DISABLED
5 #define BUTTON DISABLED
6 #define CAMERA DISABLED
7 #define CONSOLE DISABLED
8 #define FINGERPRINT DISABLED
9 #define GYROSCOPE DISABLED
10 #define LED DISABLED
11 #define LIGHT_SENSOR DISABLED
12 #define MOISTURE_SENSOR DISABLED
13 #define PINS DISABLED
14 #define PROXIMITY DISABLED
15 #define PWM DISABLED
16 #define RGBLCD DISABLED
17 #define SERVO DISABLED
18 #define SOUND_RECORDER DISABLED
19 #define TEMPERATURE ENABLED
20
21 // frequency to read sensor values in µs
22 const unsigned long SENSOR_UPDATE_FREQ = 50000;
23 const unsigned long IMU_READ_FREQ = 5000;
24 const double IMU_FILTER_ALPHA = 0.5; //Alpha for accelerometer low pass filter
25
26 unsigned long nextSensorUpdate;
27 unsigned long nextIMURead;
28 double dt;
29
30 const uint8_t BITS[8] = { 0x01, 0x02, 0x04, 0x08, 0x10, 0x20, 0x40, 0x80 };
31 const uint8_t MASK[8] = { 0xFE, 0xFD, 0xFB, 0xF7, 0xEF, 0xDF, 0xBF, 0x7F };
32
33 #include "common.h"
```

Next, you should complete the [App Inventor + IoT Basic Connection](#) tutorial to make a basic connection to the Arduino device. If you prefer, you can download the completed .aia file [here](#).

The remaining steps all build off of the the starter code for Basic Connection tutorial and .aia:


- Drag a **Label** from the User Interface Palette and drop it between **LabelStatus** and **ListBLE**
  - Rename the **Label** "LabelData".
  - Change its text to "Data: ".



- Download the [Arduino101](#) extension pack to your computer.
- In the Palette, click on Extension at the bottom and then on "Import extension" and then "Choose File". Find the file on your computer and upload it.
- Add the **Arduino101Humidity** extension to your app by dragging it onto the Viewer (the humidity sensor measures both humidity and temperature).

Next, we need to let App Inventor know which pin on the Grove board the temperature sensor is connected to.


- Click on **Arduinio101Humidity1** in the Components pane.
- In the Properties pane, click on BluetoothDevice and select **BluetoothLE1**.
- Under **Pin**, enter the digital pin that matches the one the temperature sensor is plugged into on the Grove board (in this case D4).
  - *Note: You only need to put the number (4), not the letter 'D'*



## Now switch to the Blocks Editor view

First, we want to request data updates when the sensor value on the Arduino changes.

- from `Arduino101HumiditySensor1` in the Blocks pane, add **call `Arduino101Humidity1.RequestTemperatureUpdates`** to the existing **when `BluetoothLE1.Connected`** block from the Basic Connection tutorial.



Next, we need to store the data we receive from the sensor. From the Variables drawer in the docs pane, drag an **initialize global name to** block and name it "Temperature". From the Math drawer add a number block and set it to "0". We'll use this to keep track of the sensor value.




Let's make a new procedure to display the current readings in the **LabelData** when we get new data. You can create a procedure by dragging out a purple procedure block from the Procedures drawer in the Blocks pane. Let's rename it **updateDataLabel**.

- from `LabelData` in the Blocks pane, add **set `LabelData.Text` to**.
- from the Text drawer connect a **join** block.
  - From the Text drawer, connect a text block and type **"Temperature: "**
  - From the Variables drawer connect a **get global Temperature**.



Finally, we need to call the procedure when this data is received.

- From the Arduino101Humidity1 drawer in the Blocks pane, drag **when Ardunio101Humidity1.TemperatureReceived**
  - from the Variables drawer, add **set global Temperature**.
  - Hover over the orange "temperature" in **.TemperatureReceived** to see the **get temperature** block. Drag the **get temperature** block from this window and snap to **set global Temperature**.
  - from the Procedures drawer, add **call updateDataLabel**.



Your app should now be working! Connect your Android device using the companion (if you haven't already). Test it out by closing your hand around the sensor. If it is working, you should see the data label change (but probably very slowly).

