


# App Inventor + IoT: Setting Up Your Arduino

In order to make the Arduino 101 to work with App Inventor + IoT we need to do a bit of setup. Most of this you will only need to do once.

- If you haven't already, install the Arduino Integrated Development Environment (IDE) ([Link](#))
- Now open up the IDE and open the **AIM-for-Things-Arduino101.ino** file (the Arduino file for App Inventor), which you can download [here](#).
  - *Note: If another file is open (often named "sketch\_today's date" you can close it once you open the AIM-for-Things-Arduino101 file.)*
  - You should see a screen that looks very similar to the picture below:




```
AIM-for-Things-Arduino101 | Arduino 1.8.1
AIM-for-Things-Arduino101 $ Accelerometer.hh Button.hh Camera.hh Console.hh Fingerprint.hh yros
1 #define NAME "App Inventor" // no more than 11 characters
2 #define DEBUGGING ENABLED
3
4 #define ACCELEROMETER DISABLED
5 #define BUTTON DISABLED
6 #define CAMERA DISABLED
7 #define CONSOLE DISABLED
8 #define FINGERPRINT DISABLED
9 #define GYROSCOPE DISABLED
10 #define LED ENABLED
11 #define LIGHT_SENSOR DISABLED
12 #define MOISTURE_SENSOR DISABLED
13 #define PINS DISABLED
14 #define PROXIMITY DISABLED
15 #define PWM DISABLED
16 #define RGBLCD DISABLED
17 #define SERVO DISABLED
18 #define SOUND_RECORDER DISABLED
19 #define TEMPERATURE DISABLED
20
21 // frequency to read sensor values in µs
22 const unsigned long SENSOR_UPDATE_FREQ = 50000;
23 const unsigned long IMU_READ_FREQ = 5000;
24 const double IMU_FILTER_ALPHA = 0.5; //Alpha for accelerometer low pass filter
25
26 unsigned long nextSensorUpdate;
27 unsigned long nextIMURead;
28 double dt;
29
30 const uint8_t BITS[8] = { 0x01, 0x02, 0x04, 0x08, 0x10, 0x20, 0x40, 0x80 };
31 const uint8_t MASK[8] = { 0xFE, 0xFD, 0xFB, 0xF7, 0xEF, 0xDF, 0xBF, 0x7F };
32
33 #include "common.h"


4 Arduino/Genuino 101 on /dev/cu.usbmodem1441
```

Now we're going to install some libraries that are necessary to run Arduino with App Inventor.


- *Note: While you might not need these libraries for every project they are a good baseline and are required for the [Healthy Plant App](#)*
- Click on the **Sketch** dropdown menu, hover over **Include Library**, and then select **Manage Libraries**



- In *Filter your search...* type "DHT-sensor-library" and click Install.




- Now, let's do the same for “Adafruit Unified Sensor” (you might need to scroll down to find the right one)



Getting the Grove LCD RGB Backlight working is a bit different.


- First you need to download the library file [here](#) to your computer.
- In the Arduino IDE menu, click on **Sketch > Include Library > Add .ZIP Library**
- Find the file on your computer and upload it




To confirm the library was successfully installed click back to manage libraries:

**Sketch > Include Library > Manage Libraries**

- In the search bar type in "Grove LCD"
  - You should see "Grove\_LCD\_RGB\_Backlight-master" as **Installed**




Now, if you haven't already, you should now plug in your Arduino to your computer.




Next, you need to select the correct Arduino board (Arduino/Genuino 101).

- Under the Tools menu go to the Board sub-menu. At the bottom if you see "Arduino/Genuino 101" then select it. If not, follow the steps below.




If you don't see the Arduino/Genuino 101, select Board Manager from the same sub-menu mentioned above.




In the search bar, type "101" and then select the "Intel Curie Board by Intel"

- Click on the "Select version" dropdown, and select 1.0.7
  - *Note: DO NOT use later versions of the firmware*
- Click on "Install"




Next we need to select the port that the Arduino IDE (programming environment) will use to talk to the Arduino.

- First, make sure the Arduino is plugged into your computer.
- Under the Tools menu, select the "Port" sub-menu
- For Macs, under the "Port" sub-menu, you should see an option that starts with:
  - `/dev/cu.usbmodem...`
- For PC computers, you should see an option that starts with:
  - **COMX (Arduino/Genuino 101)** with X being some number from 1-8
- Select this option
  - *Note: It sometimes takes a minute after you plug in your Arduino for the Port to show up under the submenu*





To run the Arduino program we need to send it to the board. To do this, click on the arrow button in the top left corner of the program window.



Once you have sent the code to the Arduino board, your App Inventor app can interact with the Arduino. Follow any of the How To's to make an app to control sensors on your board.